

---

Suprtool 5.4.16 for HP-UX:

# Change Notice

by Robelle Solutions Technology Inc.



Program and manual copyright © 1981-2012 Robelle Solutions Technology Inc.

Permission is granted to reprint this document (but not for profit), provided that copyright notice is given.

Qedit and Suprtool are trademarks of Robelle Solutions Technology Inc. Oracle is a trademark of Oracle Corporation, Redwood City, California, USA. Other product and company names mentioned herein may be the trademarks of their respective owners.



Robelle Solutions Technology Inc.  
Suite 372, 7360 137 Street  
Surrey, BC Canada V3W 1A3

Phone: 604.501.2001  
Fax: 604.501.2003

E-mail: [sales@robelle.com](mailto:sales@robelle.com)  
E-mail: [support@robelle.com](mailto:support@robelle.com)  
Web: [www.robelle.com](http://www.robelle.com)

# Contents

<b>Introducing Suprtool Version 5.4.16</b>	<b>5</b>
Overview .....	5
Highlights in Suprtool 5.4.16.....	5
Highlights in Suprtool 5.4.15.....	5
Highlights in Suprtool 5.4.13.....	5
Highlights in Suprtool 5.4.12.....	6
Highlights in Suprtool 5.4.11.....	6
Highlights in Suprtool 5.4.10.....	6
Highlights in Suprtool 5.4.01.....	6
Highlights in Suprtool 5.4.....	6
Itanium vs PA_RISC .....	7
Compatibility .....	9
Itanium Compatibility.....	9
CPU Serial Number (uname).....	9
Documentation.....	9
<b>Installation</b>	<b>10</b>
Overview .....	10
Installation Instructions.....	10
Installation Assistance .....	10
<b>Enhancements in Version 5.4.16</b>	<b>11</b>
Introduction .....	11
Set Oracle .....	11
Data Items Support .....	11
<b>Enhancements in Version 5.4</b>	<b>12</b>
Introduction .....	12
Eloquence Loading .....	12
Output Command.....	12
<b>Enhancements in Version 5.3</b>	<b>13</b>
Introduction .....	13
Add Command.....	13
SpaceNull.....	13
PassShift .....	13
<b>Bugs Fixed</b>	<b>14</b>
Bugs Fixed In Suprtool 5.4.16.....	14
Bugs Fixed In Suprtool 5.4.15.....	14
Bugs Fixed In Suprtool 5.4.13.....	14
Bugs Fixed In Suprtool 5.4.12.....	14

Bugs Fixed In Suprtool 5.4.01 .....	14
Bugs Fixed In Suprtool 5.3.12 .....	14

# Introducing Suprtool Version 5.4.16

---

## Overview

Use Suprtool/UX to read, select, and sort data from Oracle, Allbase and Eloquence databases and data files with fixed-length records. Suprtool/UX is designed to be similar to Suprtool for MPE while providing necessary HP-UX features.

Suprlink/UX provides high-speed data-file linking based on a sort key. Use STExport to convert fields in a self-describing input file into an output file that can be imported into different applications.

---

## Highlights in Suprtool 5.4.16

- Set Oracle DataBug On | Off has been added to mimic the incorrect behaviour of writing double the number of bytes in versions 5.1 thru 5.4 and if no extract commands were in place and either set ifouroutput or set oracle integer were on.
- The \$edit function did not work properly with alpha based edit masks and if the target was greater than 32 characters.

---

## Highlights in Suprtool 5.4.15

- Set Oracle Integer on and Set Ifouroutput on no longer writes out double the calculated record size when the output option is output,data, and the input source is an Oracle table.

---

## Highlights in Suprtool 5.4.13

- The List command to a file with headings and title would print some empty lines and the string "STEXPORT.PUB.ROBELLE" instead of the titles and headings. (PA\_RISC HP-UX version only)

---

## Highlights in Suprtool 5.4.12

- Set Fastread now has a default value of off.
- The number of Fields/items support in the HP-UX version of Suprtool has been reduced from 300 to 268.
- Suprtool would abort in the middle of an fwrite to the sort scratch file.
- Suprlink for AMXW would fail on a JOIN command suddenly after applying a patch to libc.

---

## Highlights in Suprtool 5.4.11

- STExports Escape command has been re-written.

---

## Highlights in Suprtool 5.4.10

- Suprtool for HP-UX now supports 300 fields in both an Eloquence database and SD files.
- STExport for HP-UX now supports 300 fields in an SD file.
- Suprlink for HP-UX now supports 300 fields in an SD file.
- The PA\_Risc version of Suprtool, Suprlink and STExport now prints out the Build version number.

---

## Highlights in Suprtool 5.4.01

- Suprtool for HP-UX on Itanium would abort when sorting very large records.

---

## Highlights in Suprtool 5.4

- Suprtool for HP-UX on Itanium now properly supports \$atoc and \$etoc. (Itanium Version Only)
- Suprtool would encounter problems when reading record sizes greater than 13700 bytes. (Itanium Version Only)
- Suprtool for HP-UX on Itanium would incorrectly coerce the number negative 65536 from Binary to Decimal and Decimal to Binary. (Itanium Version Only)
- Suprtool for HP-UX on Itanium would fail with an HPPAC error if the field had spaces when reading a display field.
- The Eloquence loading algorithm has been changed to make another attempt at loading the routines.
- The Output command has been enhanced to accept the new verb "else", which when invoked it will write out the records that do not qualify and write them to an external file.

- Suprtool did not properly clear the data field information from a table at the end of a task.
- Suprtool did not properly zero out a packed field target when an table entry was not found when extracting data from a table.

---

## Itanium vs PA\_RISC

There are two types of machines that HP has that run HP-UX, the older machines are based on the PA\_RISC chip and the new machines that use the Itanium (and Itanium 2 chips). There are also program files that are specific to each chip. PA\_RISC programs can run on both PA\_RISC and Itanium machines, however, Itanium programs can only run on Itanium machines.

Any program that runs on Itanium must utilize libraries that match its own program type. Therefore if a PA\_RISC program runs on Itanium and looks for a library, it must find/load the PA\_RISC version of the libraries that it needs and conversely an Itanium program must load the libraries specific to its type.

### How to Tell what Machine I am on?

There are many ways to tell what kind of machine you are on, here are a couple:

```
uname -m
getconf MACHINE_MODEL
```

In each case the Itanium machine will typically say ia64 somewhere in the result of the above two commands. PA\_RISC machines typically say "9000" somewhere in the string.

### What is the Program File Type?

Since there are two types of machines there are also at least two types of program files. Suprtool is primarily either PA\_RISC 1.1 or ELF-32 / IA64 which is also known as Itanium. To determine the type of program file you can use the file command:

#### Itanium

```
file suprtool
suprtool:      ELF-32 executable object file - IA64
```

#### PA\_RISC

```
file suprtool
suprtool:      PA-RISC1.1 executable dynamically linked -not stripped
```

The PA\_RISC binary can run on both platforms but you need to have PA\_RISC libraries for Eloquence or Oracle if you are using the Oracle module. An Itanium binary will not run on a PA\_RISC machine and will fail with "cannot execute".

Of course we've made a provision to identify if you are running the ia version of Suprtool in the banner and verify command with the ia after the UX :

```
SUPRTOOL/UXia/Copyright Robelle Solutions Technology Inc. 1981-2009.
(Version 5.2 Internal) MON, JUN 8, 2009, 11:26 AM Type H for help.
```

### PA\_RISC Loading

Suprtool by default looks in the libraries in any of the directories named in SHLIB\_PATH. For example to insure that Suprtool resolves the library loads you can set the SHLIB\_PATH system wide in your /etc/profile file in the following manner:

```
export SHLIB_PATH=/opt/eloquence6/lib/pa11_32:/opt/oracle/lib
```

If you do not have the SHLIB\_PATH variable set to a value where the libraries can be found, Suprtool will then try to load from their default names locations. For Eloquence the default location is `:/opt/eloquence6/lib/pa11_32`.

The Oracle interface will first try to load `libclntsh.so` and then attempt to load `libclntsh.sl` from `$ORACLE_HOME/lib32/libclntsh.sl`.

### Itanium Loading

You can change Suprtool to pay attention to LD\_LIBRARY\_PATH and use `dlopen` to load libraries by setting the environment variable:

```
export ROBELLE_DYN_LOAD =Y.
```

It is generally advisable to use `DLOPEN` or the `ROBELLE_DYN_LOAD` option when using the Itanium version. The PA\_RISC version of Suprtool can use either type of loading, the default or the `dlopen` method invoked with `ROBELLE_DYN_LOAD`.

The Itanium version will make one more attempt at loading the Eloquence libraries from `hpux32/libimage3k.sl` and `hpux32/libeqdb.sl` as most users are setting `SHLIB_PATH` and `LD_LIBRARY_NAME` pointing to the lib directory.

### Running the PA\_RISC version on Itanium:

You can of course run the PA\_RISC version of Suprtool, however, given that the PA\_RISC version requires `SHLIB_PATH` to point to PA\_RISC libraries may go against the configuration necessary for other programs that may need `SHLIB_PATH` to point to Native Itanium libraries.

The solution to this is fairly simple, you can create a command file (let's say `/opt/robelle/cmd/suprtool`) that runs `suprtool` for you, of course you need to insure your path variable has `/opt/robelle/cmd` before `/opt/robelle/bin`.

You can then have the following commands in the `/opt/robelle/cmd/suprtool` command file:

```
export SAVED_SHLIB_PATH=$SHLIB_PATH
export SHLIB_PATH=/opt/oracle/pa_risc/lib:/opt/eloquence/lib/pa11_32
/opt/robelle/bin/suprtool $@
export SHLIB_PATH=$SAVED_SHLIB
```

Essentially all it does save the current `SHLIB_PATH` setting, sets it to point to PA\_RISC libraries, runs `suprtool` and then resets the library back.

### Suprtool for Itanium

Now that you know all about PA\_RISC and Itanium you do need to be aware of what Suprtool for Itanium is in terms of new code and risk for potential issues. Suprtool for Itanium is completely in C code. This does not mean that it is all new C code however, the majority of the Suprtool code is still based on SPL, but is converted to C, using Allegro's SPLASH compiler.

So while the C code is new it is based on the original SPLash code, however, given differences between C and SPLash not all code can be automatically converted in some cases. We worked closely with Allegro to find ways to have the source code work and address the various issues that came up. The entire time Allegro improved the SPLash to C converter.

So while we are based on the original Suprtool we do have new code paths in the Native Itanium version and other potential issues where the C code might not work in exactly the same manner as the SPLash code.

Having said that we have tested this against our test suites, and improved and added a large number of tests to our HP-UX test suites.

---

## Compatibility

Fastread option is now set to Off for Suprtool for HP-UX. The Dynamic loading version of Suprtool the option is set to off.

Suprtool production versions 5.1 thru 5.4.01 would incorrectly double the record size for an output,data file when either Set Ifouroutput or Set Oracle Integer were on. This has been fixed but if your script accounted for a doubled record size this may cause an issue as we no longer incorrectly write out double the bytes. If you want to have the old bug behaviour to be re-instated you can Set Oracle DataBug On. The default for this setting is off.

---

## Itanium Compatibility

There are a couple of differences in the Itanium version of Suprtool, which you need to be aware of.

**The DBEdit module is not available in the Itanium versions of Suprtool. This module is invoked by the EDIT command.**

**The layout for the Verify command is slightly different then the PA-RISC versions of Suprtool.**

---

## CPU Serial Number (uname)

This program runs only on CPUs whose serial numbers have been encoded (the "uname" on HP-UX). If it fails to run and you get an "invalid HPSUSAN" error message, contact Robelle for assistance, via [support@robelle.com](mailto:support@robelle.com) or the support number at 1-800-453-8970.

---

## Documentation

The user manual contains the full description of all the Suprtool suite of products including Dbedit, Suprlink, STExport, and Suprtool2, as well as usage tips and commands for each. The manuals are up-to-date with all the latest changes. To see only the changes in the latest version, see the "What's New" section of the manual.

You can download our manuals and Change Notices in various formats and order printed (hardcopy) manuals from our web site at:

<http://www.robelle.com/library/manuals/>.

# Installation

---

## Overview

The following instructions describe the installation process of a new Suprtool release. The new version overwrites an existing version of Suprtool on your HP-UX system.

---

## Installation Instructions

There are typically two main types of installations. The first and most often utilized is the Download instructions. You can find the HP-UX download install instructions here:

<http://www.robelle.com/downloads/install-sxpre.html>

Tape installation instructions can be found here:

<http://www.robelle.com/support/install/tape/sxpre.html>

---

## Installation Assistance

If you have any questions or run into any problems, please call us. Technical support is available on weekdays from 8 a.m. to 4 p.m. Pacific time at 1.800.453.8970.

Technical support can also be obtained via e-mail at: [support@robelle.com](mailto:support@robelle.com) If your new version of software will not run, you can page someone from technical support by calling the 1.800 number, or you can typically easily run extend with the disaster option to tide you over until business hours. Instructions for this are available at:

<http://www.robelle.com/disaster/>

# Enhancements in Version 5.4.16

---

## Introduction

Suprtool is constantly being updated with new features. The following section describes the new enhancements to Suprtool since Suprtool 5.4.

---

## Set Oracle

Suprtool now has a command done strictly for compatibility. In Suprtool 5.1, thru to 5.4, the output record size written out will be double the actual size when the input source was an Oracle table, either Set IFourOutput was on or Set Oracle Integer was on and no extract command were used and Output,link was not used.

**Set Oracle DataBug On** can be turned on to write out double the calculated record size in case some customers had code that relied on the larger record size. The default however, is off. [5.4.16]

---

## Data Items Support

Suprtool now supports 268 data items in both Eloquence datasets and SD files. STExport and Suprlink have also been updated to support the increased number of data items.

The number of data items supported has been reduced due to a heap corruption issue which cause an fwrite to the sort scratch file. [5.4.12]

# Enhancements in Version 5.4

---

## Introduction

Suprtool is constantly being updated with new features. The following section describes the new enhancements to Suprtool since Suprtool 5.3.

---

## Eloquence Loading

The algorithm for Eloquence routine loading has changed slightly on Itanium. Suprtool will attempt to load `hpux32/libimage3k.sl` and `hpux32/libeqdb.sl` on the second attempt to load the libraries. The algorithm is that Suprtool will first try to load the files individually, then `hpux32/libimage3k.sl` and then an attempt at the fully qualified filename.

---

## Output Command

The Output command has been enhanced to accept the new verb "else", which when invoked it will write out the records that do not qualify and write them to an external file.

Consider the following task:

```
base mydb
get customers
if custno >= "50A"
out mycusts,link,else
xeq
```

Suprtool will create two files one called `mycusts` and `mycusts.else`, technically it creates four files as they are both self-describing files and have the meta information file in the ".sd" files, however the data is put in the output files. The else file gets named automatically by Suprtool. In the example above the following files would be created :

```
mycusts
mycusts.sd
mycusts.else
mycusts.else.sd
```

This works for flat files, Eloquence (via `get` and `chain`) and Oracle databases via `Select` and self-describing files. A `.else` file will not be created when using `output,num` and `output,key`. The task will still complete but a warning will be printed indicating that `,else` cannot be used with the `,num` or `key` options.

Suprtool will throw an error when using `output,else` with either the `duplicate` command or a `duplicate` option on the output command.

The ".else" file will be in the same format as the output file.

# Enhancements in Version 5.3

---

## Introduction

Suprtool is constantly being updated with new features. The following section describes the new enhancements to Suprtool since Suprtool 5.2.10

---

## Add Command

The Add command which allows for adding data to an Oracle table now allows for the syntax of Ownername.Tablename. The single syntax of just giving the table name will work as it always has.

---

## SpaceNull

Suprtool has a new setting called Set Oracle SpaceNull, which when on puts spaces in any byte, Char or Date (Oracle Date) fields instead of the nulls. The default behaviour is off.

---

## PassShift

Suprtool now has the command Set Oracle PassShift Off which turns off the default behaviour of up-shifting Oracle passwords. This is to accommodate Oracle 11 which allows case sensitive passwords. The first pass on this was to allow the syntax of:

```
open oracle suprtest suprpas
```

We now honour Set Oracle PassShift for the syntax that includes the service name:

```
open oracle suprtest/suprpas@servname
```

# Bugs Fixed

---

## Bugs Fixed In Suprtool 5.4.16

**\$edit function.** The \$edit function did not work well with alpha based edit masks and if the target was greater than 32 characters.

---

## Bugs Fixed In Suprtool 5.4.15

**Output,data.** Suprtool would write out double the calculated record size when set oracle integer was on or set ifouroutput was on, and output,data option was used and no extract commands were specified and the input source was an Oracle table.

---

## Bugs Fixed In Suprtool 5.4.13

**List Command.** The List command on Suprtool for HP-UX on PA\_RISC would not print the specified headings and title for list command to a file.

---

## Bugs Fixed In Suprtool 5.4.12

**Sorting.** Suprtool for HP-UX on PA\_RISC would abort when sorting a file with an output record size of 39 bytes and only on some machines, with fastread on.

---

## Bugs Fixed In Suprtool 5.4.01

**Sorting.** Suprtool for HP-UX on Itanium would abort when sorting very large records.

---

## Bugs Fixed In Suprtool 5.3.12

**Packed Data.** Suprtool for HP-UX on Itanium would incorrectly coerce the number negative 65536 from Binary to Decimal and Decimal to Binary.

**Table Command.** Suprtool did not properly clear the data field information from a table at the end of a task.

**Extract from Table.** Suprtool did not properly zero out a packed field target when an table entry was not found when extracting data from a table and the Packed field was P12 or higher.